

LAB USE ONLY

Labial Rx

Dr. _____ Acct # _____

Address _____

City, State, Zip _____

Patient _____

Tel # _____ Fax # _____

E-Mail _____

Shipped _____ Placement Date _____

(PLACEMENT DATE SHOULD BE 1-2 DAYS BEFORE ACTUAL INSERTION DATE)

Please Ship Extra

Pre-Paid Bags Shipping Boxes Prescription Sheets

Submitted scans digitally through:

Lythos iTero 3M Box Other _____

Special Instructions:

1. Choose Placement

PLACEMENT OPTIONS

Standard Dr. Damon

PLEASE INDICATE WHERE TO SECTION

Do Not Section Tray Section At The Midline Section Distal to Cuspids


Allesee Orthodontic Appliances - 13931 Spring Street - Sturtevant, WI 53177
Phone 1-800-262-5221 - Fax 262-886-6879 - International 262-886-1050

2. Select Slot Relationships

Standard Slot Relationships Are Illustrated Below.

Please Indicate Any Changes On Chart

Circle teeth to be banded by Doctor. Mark on Teeth not to be Treated



3. Misc.


BRACKET & TRAY SYSTEM STANDARDS

Brackets are supplied by office, and sent to AOA

Mesh Pad will have Custom Composite Base

TWO PIECE SYSTEM

Clear soft Vinyl w/Clear Hard Support Tray



4. Indirect Bonding with Light Cure Adhesive

Indirect Bonding with Light Cure Adhesive

1. Paint OrthoSolo® (Ormco) on the back of the brackets in the Indirect Bonding trays. Blow excess off after 30 seconds. Immediately place a small amount of Enlight LV® (Ormco) light cure adhesive on back of the brackets. Place under an orange cover or remove from light source.
2. Clean all teeth using pumice and prophylaxis and rinse.
3. Place dry angles and Nola lip retractors.
4. Micro-etch labial surfaces of posterior teeth.
5. Etch labial surfaces of posterior teeth.
6. Rinse thoroughly.
7. Dry teeth with tooth dryer.
8. Paint OrthoSolo® on teeth. Do Not Cure.
9. Place Indirect bonding tray onto mandibular arch seating firmly.
10. Cure each bracket at least 10 seconds at the Burst Cure setting with the Optilux 501® (Demetron Corp) while pressing moderately on each bracket.
11. Repeat for maxillary arch.
12. To remove trays, first remove hard outer tray, then gently peel soft tray from each bracket while holding a finger on bracket. Repeat on maxillary arch.
13. Remove excess adhesive with slow speed and check interproximal contacts with floss.

Doctor Signature _____



Laboratory Use Only

IB _____

IB _____

IB _____

IB _____

IB _____

IB _____

IB _____

IB _____

IB _____

IB _____

IB _____

IB _____

SHIP _____